

Release note for Server Imaging Utility March 2017

Notes

BTBackup (now moved into the Server Manager) will now backup the BlackTrax folder in btuser instead of the documents folder. This means that the backup server needs a shared BlackTrax folder in order for the Server Manager to register it. This folder is shared by default in this image.

Included BlackTrax Release:

v2.1.2

Dongle Date Requirement:

July 26th 2016

Major changes:

- Server Manager, an easier way to back up your server and configure the profile
 - The new BlackTrax folder is what is now backed up instead of the documents folder
- Fixed the issue where newer versions of Chrome would be blocked

Known issues:

- Motive may freeze the first time it's launched

Features and Fixes:

Bug

- *Fixed: Latest Chrome versions are no longer blocked*
- *Fixed: Domain Firewall is now disabled*

New Feature

- *Server Manager application that replaces BTBackup and BlackTrax Profile Manager*
 - *View currently installed versions of all BlackTrax applications*
 - *Convenient access for license and library folder locations*
 - *Rename server directly from this application*
 - *Assign the 'Main' or 'Backup' profile to your server*
 - *An option to also change the name of server to match the profile has been added*
 - *Backup the BlackTrax folder of the main server to the backup server's BlackTrax folder and create an archive of old files on the backup*
 - *Progress reporting highlighting how many files are left*
 - **Note:** *The backup portion of the Server Manager will no longer use the documents folder, it will now use the new BlackTrax folder*
 - *View all NICs and their statuses*
 - *View system information including image version*

- *New IP address for Device Manager – 10.133.5.9 added to the BTNet NIC*
- *Added sACNView to the server*

Improvement

- *New installation process*
 - *Displays license information and status*
 - *Reporting of installation process and status of each step*
 - *System will automatically reboot into Windows without first needing to remove the boot media*
- *New setup process upon first server boot (configuration of the server is moved to this step now, instead of the installation process)*
 - *Server will be named either 'BTSERVER-MAIN' or 'BTSERVER-BACKUP' depending on configuration*
 - *Main or Backup wallpaper will automatically be applied to the server depending on configuration*
- *New BlackTrax folder in the btuser folder*
- *Monitor now starts up automatically*
- *Updated Wireshark to version to 2.2.5*
- *USB Autoplay is now disabled by default*

Design Review

- *New startup animation upon first boot*
- *New imaging utility wallpaper*
- *Server Manager is pinned to the Start Menu and Task Bar*
- *Themes default the wallpaper to stretch instead of fill now*
- *Monitor is visible in the main Task Tray by default*